

KidDesk 1.1 Update

This is a new, upgraded version of *KidDesk*. Some of the new features on your disk are not documented in the Guide.

New Features Include:

- Password-protected desks
- Secure auto-start that can be set from the Adult Section of *KidDesk**
- Document access options*
- Disk eject options
- Add Application options
- 16-color support

*System 7 only

Control these features from the KidDesk Adult Section (page 18):

Kid Passwords: You can protect each desk with a password by turning "Password" on in the child's Add Kid or Kid Settings dialog box (pages 20 and 23). Then, either set a specific password by entering it in the box, or leave the box empty to allow the child to set a password the first time the desk is entered. Note: If you set an Adult Password (page 26), that password will work as a master kid password, allowing you to enter any password-protected desk or change a child's password if it has been forgotten.

Auto-start: System 7 users can set *KidDesk* to run automatically each time the computer is turned on by choosing *Startup Options* from the Options menu, and then selecting "Startup to KidDesk." (System 7 users, please disregard the instructions in Step #7, page 4.) System 6 users, see Step #7 of *Installation*, page 4, to set *KidDesk* to auto-start.

Document Access Options: To control where your kids can open and save documents, choose *Document Access Options* from the Options menu. When document access is limited, kids will be able to open or save documents only where you have indicated. For example, you can allow your child to open and save documents only from floppy disks.

- To allow kids to open and save documents anywhere on the hard drive or floppy disk, click "Open/Save Anywhere."

- To restrict where kids can open and save documents, click "Open/Save Limited to." Then click to place or remove check marks in the Floppy Disk, Kid's Folder (each kid has a personal folder in the *KidDesk* folder on the hard drive), or Shared Folder (any folder you specify) check boxes. (An "X" in the check box indicates that kids **can** access that area.)

Disk Eject Options: To control whether your child can eject floppy disks and CD-ROM discs, choose *Disk Eject Options* from the Options menu. Place an "X" in the "Display CD-ROM eject icon" or "Display floppy disk eject icon" check boxes to allow kids to eject disks by clicking a disk icon on their desks. The icon only appears on the desk if a disk is in the drive. If "Eject floppy disk when exiting desk" is checked, the disk in the internal drive is automatically ejected each time a kid exits a desk and returns to the Opening Screen.

Add Application: Place applications on your child's desk by choosing *Add Application* from the Application menu. (See page 25 of the Guide for more information.)

- To search the drive automatically (*KidDesk* displays an alphabetical list of all applications on the drive), choose "Auto Search," and use the pop-up menu to indicate which drive you wish to search. Click "OK." Then, follow the directions on page 25 to select the applications.
- To search the drive manually, choose "Manual Search," and click "OK." Then, use the standard "Open File" dialog to find the application you wish to add.

Having Problems?

If you encounter any difficulties in using the program, please refer to *Troubleshooting* in your *KidDesk Guide* (page 37). If that page does not answer your questions, you can reach Edmark's Technical Support Team at (206) 556-8480.